

# **Sample Parameterized Cells Installation and Reference**

**Product Version ICADVM20.1  
October 2020**

© 2020 Cadence Design Systems, Inc. All rights reserved.  
Printed in the United States of America.

Cadence Design Systems, Inc., 555 River Oaks Parkway, San Jose, CA 95134, USA

**Trademarks:** Trademarks and service marks of Cadence Design Systems, Inc. (Cadence) contained in this document are attributed to Cadence with the appropriate symbol. For queries regarding Cadence's trademarks, contact the corporate legal department at the address shown above or call 1-800-862-4522.

All other trademarks are the property of their respective holders.

**Restricted Print Permission:** This publication is protected by copyright and any unauthorized use of this publication may violate copyright, trademark, and other laws. Except as specified in this permission statement, this publication may not be copied, reproduced, modified, published, uploaded, posted, transmitted, or distributed in any way, without prior written permission from Cadence. This statement grants you permission to print one (1) hard copy of this publication subject to the following conditions:

1. The publication may be used solely for personal, informational, and noncommercial purposes;
2. The publication may not be modified in any way;
3. Any copy of the publication or portion thereof must include all original copyright, trademark, and other proprietary notices and this permission statement; and
4. Cadence reserves the right to revoke this authorization at any time, and any such use shall be discontinued immediately upon written notice from Cadence.

**Disclaimer:** Information in this publication is subject to change without notice and does not represent a commitment on the part of Cadence. The information contained herein is the proprietary and confidential information of Cadence or its licensors, and is supplied subject to, and may be used only by Cadence's customer in accordance with, a written agreement between Cadence and its customer. Except as may be explicitly set forth in such agreement, Cadence does not make, and expressly disclaims, any representations or warranties as to the completeness, accuracy or usefulness of the information contained in this document. Cadence does not warrant that use of such information will not infringe any third party rights, nor does Cadence assume any liability for damages or costs of any kind that may result from use of such information.

**Restricted Rights:** Use, duplication, or disclosure by the Government is subject to restrictions as set forth in FAR52.227-14 and DFAR252.227-7013 et seq. or its successor.

---

# Contents

---

<u>Preface</u> .....	5
<u>Scope</u> .....	6
<u>Licensing Requirements</u> .....	6
<u>Related Documentation</u> .....	6
<u>What's New and KPNS</u> .....	6
<u>Installation, Environment, and Infrastructure</u> .....	6
<u>Technology Information</u> .....	7
<u>Virtuoso Tools</u> .....	7
<u>Additional Learning Resources</u> .....	7
<u>Video Library</u> .....	7
<u>Virtuoso Videos Book</u> .....	7
<u>Rapid Adoption Kits</u> .....	8
<u>Help and Support Facilities</u> .....	8
<u>Customer Support</u> .....	8
<u>Feedback about Documentation</u> .....	9
<u>Typographic and Syntax Conventions</u> .....	10
<u>1</u>	
<u>Overview and Installation</u> .....	11
<u>About the Sample Parameterized Cells</u> .....	11
<u>Installing the Sample Parameterized Cells</u> .....	12
<u>Install Sample Pcells in One Technology Library</u> .....	12
<u>Validating the Installation</u> .....	25
<u>Loading Pcells from the libInit.il File</u> .....	25
<u>Modifications Made to the Technology File</u> .....	26
<u>Layer Correspondence Parameters in techParams</u> .....	27
<u>Physical DRC Rules</u> .....	27
<u>Device Classes</u> .....	28

## Sample Parameterized Cells Installation and Reference

---

### 2

<u>Sample Parameterized Cells Reference</u> .....	29
<u>Modifying Pcell Parameter Values</u> .....	29
<u>spcbentnmos, spcbentpmos</u> .....	30
<u>spccap</u> .....	32
<u>spcinv</u> .....	35
<u>spcnmos, spcpmos</u> .....	37
<u>spcnpn</u> .....	41
<u>spcpnp</u> .....	42
<u>spcpres</u> .....	44
<u>spcres</u> .....	46
<u>spcsimple_nmos, spcsimple_pmos</u> .....	49

### A

<u>Building Pcells with ROD Functions</u> .....	53
<u>Multipart Paths, Subpaths, and Subrectangles</u> .....	53
<u>Path Stitching with ROD Functions</u> .....	54

---

# Preface

---

This manual contains information about installing and modifying a collection of sample parameterized cells (Pcells) built procedurally with relative object design (ROD) functions of the Cadence® SKILL programming language.

Using these sample Pcells requires knowledge of the Virtuoso layout editor and the SKILL programming language and its ROD functions. The following documents provide more information on these tools.

This user guide is aimed at developers and designers of integrated circuits and assumes that you are familiar with:

- The Virtuoso design environment and application infrastructure mechanisms designed to support consistent operations between all Cadence® tools.
- The applications used to design and develop integrated circuits in the Virtuoso design environment, notably, the Virtuoso Layout Suite, and Virtuoso Schematic Editor.
- The Virtuoso design environment technology file.
- Component description format (CDF), which lets you create and describe your own components for use with Layout XL.

This preface contains the following topics:

- [Scope](#)
- [Licensing Requirements](#)
- [Related Documentation](#)
- [Additional Learning Resources](#)
- [Customer Support](#)
- [Feedback about Documentation](#)
- [Typographic and Syntax Conventions](#)

## Scope

Unless otherwise noted, the functionality described in this guide can be used in both mature node (for example, IC6.1.8) and advanced node and methodologies (for example, ICADVM20.1) releases.

Label	Meaning
(ICADVM20.1 Only)	Features supported only in ICADVM20.1 advanced nodes and advanced methodologies releases.
(IC6.1.8 Only)	Features supported only in mature node releases.

## Licensing Requirements

For information about licensing in the Virtuoso design environment, see [\*Virtuoso Software Licensing and Configuration Guide\*](#).

## Related Documentation

### What's New and KPNS

- [\*Virtuoso Parameterized Cell What's New\*](#)
- [\*Virtuoso Parameterized Cell Known Problems and Solutions\*](#)

### Installation, Environment, and Infrastructure

- [\*Virtuoso Relative Object Design User Guide\*](#)
- [\*Virtuoso Relative Object Design SKILL Reference\*](#)
- [\*Virtuoso Parameterized Cell Reference\*](#)
- [\*Virtuoso Layout Suite SKILL Functions Reference\*](#)
- [\*Cadence Installation Guide\*](#)
- [\*Virtuoso Design Environment User Guide\*](#)

## Sample Parameterized Cells Installation and Reference

### Preface

---

- [\*Virtuoso Design Environment SKILL Reference\*](#)
- [\*Cadence Application Infrastructure User Guide\*](#)

### Technology Information

- [\*Virtuoso Technology Data User Guide\*](#)
- [\*Virtuoso Technology Data ASCII Files Reference\*](#)
- [\*Virtuoso Technology Data SKILL Reference\*](#)

### Virtuoso Tools

- [\*Virtuoso Layout Suite L User Guide\*](#)
- [\*Virtuoso Layout Suite SKILL Reference\*](#)

## Additional Learning Resources

### Video Library

The [Video Library](#) on the Cadence Online Support website provides a comprehensive list of videos on various Cadence products.

To view a list of videos related to a specific product, you can use the *Filter Results* feature available in the pane on the left. For example, click the *Virtuoso Layout Suite* product link to view a list of videos available for the product.

You can also save your product preferences in the Product Selection form, which opens when you click the *Edit* icon located next to *My Products*.

### Virtuoso Videos Book

You can access certain videos directly from Cadence Help. To learn more about this feature and to access the list of available videos, see [Virtuoso Videos](#).

## Rapid Adoption Kits

Cadence provides a number of [Rapid Adoption Kits](#) that demonstrate how to use Virtuoso applications in your design flows. These kits contain design databases and instructions on how to run the design flow.

To explore the full range of training courses provided by Cadence in your region, visit [Cadence Training](#) or write to [training\\_enroll@cadence.com](mailto:training_enroll@cadence.com).

**Note:** The links in this section open in a separate web browser window when clicked in Cadence Help.

## Help and Support Facilities

Virtuoso offers several built-in features to let you access help and support directly from the software.

- The Virtuoso *Help* menu provides consistent help system access across Virtuoso tools and applications. The standard Virtuoso *Help* menu lets you access the most useful help and support resources from the Cadence support and corporate websites directly from the CIW or any Virtuoso application.
- The Virtuoso Welcome Page is a self-help launch pad offering access to a host of useful knowledge resources, including quick links to content available within the Virtuoso installation as well as to other popular online content.

The Welcome Page is displayed by default when you open Cadence Help in standalone mode from a Virtuoso installation. You can also access it at any time by selecting *Help – Virtuoso Documentation Library* from any application window, or by clicking the *Home* button on the Cadence Help toolbar (provided you have not set a custom home page).

For more information, see [Getting Help](#) in *Virtuoso Design Environment User Guide*.

## Customer Support

For assistance with Cadence products:

- Contact Cadence Customer Support

Cadence is committed to keeping your design teams productive by providing answers to technical questions and to any queries about the latest software updates and training needs. For more information, visit <https://www.cadence.com/support>.



- Log on to Cadence Online Support

Customers with a maintenance contract with Cadence can obtain the latest information about various tools at <https://support.cadence.com>.

## **Feedback about Documentation**

You can contact Cadence Customer Support to open a service request if you:

- Find erroneous information in a product manual
- Cannot find in a product manual the information you are looking for
- Face an issue while accessing documentation by using Cadence Help

You can also submit feedback by using the following methods:

- In the Cadence Help window, click the *Feedback* button and follow instructions.
- On the Cadence Online Support [Product Manuals](#) page, select the required product and submit your feedback by using the *Provide Feedback* box.

## Typographic and Syntax Conventions

The following typographic and syntax conventions are used in this manual.

<i>text</i>	Indicates names of manuals, menu commands, buttons, and fields.
text	Indicates text that you must type exactly as presented. Typically used to denote command, function, routine, or argument names that must be typed literally.
<i>z_argument</i>	Indicates text that you must replace with an appropriate argument value. The prefix (in this example, <i>z_</i> ) indicates the data type the argument can accept and must not be typed.
	Separates a choice of options.
{ }	Encloses a list of choices, separated by vertical bars, from which you <b>must</b> choose one.
[ ]	Encloses an optional argument or a list of choices separated by vertical bars, from which you <b>may</b> choose one.
[ ?argName <i>t_arg</i> ]	Denotes a <i>key argument</i> . The question mark and argument name must be typed as they appear in the syntax and must be followed by the required value for that argument.
...	Indicates that you can repeat the previous argument.
	Used with brackets to indicate that you can specify zero or more arguments.
	Used without brackets to indicate that you must specify at least one argument.
, ...	Indicates that multiple arguments must be separated by commas.
=>	Indicates the values returned by a Cadence® SKILL® language function.
/	Separates the values that can be returned by a Cadence SKILL language function.

If a command-line or SKILL expression is too long to fit within the paragraph margins of this document, the remainder of the expression is moved to the next line and indented. In code excerpts, a backslash ( \ ) indicates that the current line continues on to the next line.

---

## Overview and Installation

---

This chapter contains conceptual information about the sample parameterized cells and a guide to installing these devices into your library.

- [About the Sample Parameterized Cells](#) on page 11
- [Installing the Sample Parameterized Cells](#) on page 12
- [Modifications Made to the Technology File](#) on page 26

### About the Sample Parameterized Cells

Sample parameterized cells are layout views of devices built using relative object design (ROD) functions. A parameterized cell (Pcell) is a graphic, programmable cell that lets you create a customized instance each time you place it. The Pcells in this collection serve as examples of how you can use ROD functions to create your own Pcells. You can modify the sample Pcells to suit your specifications. The files containing the device code reside in the directory

`your_install_dir/tools/dfII/samples/ROD/rodPcells/components/device`

where `your_install_dir` is the path to the Cadence® software directory and `device` is the directory containing the code for the device you want to modify. The following table provides the directory name for all of the sample Pcells.

Device Name	Directory
spcbentnmos/spcbentpmos	bentmos
spccap	cap
spcinv	inv
spcnmos/spcpmos	mos
spcnpn	npn

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

Device Name	Directory
spcpnp	pnp
spcpres	pres
spcres	res
spcsimple_nmos/spcsimple_pmos	simple_mos

## Installing the Sample Parameterized Cells

Before you can use the sample parameterized cells, you must install them into a library. The installation script defines new device classes in your technology file and defines devices for each new class. During the installation process, you have the opportunity to specify the layer definitions and design rules for your technology.

### Install Sample Pcells in One Technology Library


Installing sample parameterized cells in different technology libraries across the technology graph can lead to conflicts. When sample parameterized cells are installed, the technology database is updated with the parameters and values (techParams). These parameters and

## Sample Parameterized Cells Installation and Reference Overview and Installation

---

values must be unique within the technology graph. The following is an example of how conflicts can be created when installing parameterized cells in different technology libraries.

Sample Pcell installation



For more information about the technology file in general, refer to the [\*Technology File and Display Resource File User Guide\*](#). For more information about the changes the installation script makes to your technology file, see [“Modifications Made to the Technology File”](#) on page 26.

At any time during the installation process you can

- Click *OK* to apply any changes you have made and exit the installation
- Click *Cancel* to stop the installation process
- Click *Previous* to go to the previous step
- Click *Next* to apply any changes and go to the next step in the installation

To install the sample parameterized cells into a library, follow the steps below.

1. Type the following in the Command Interpreter Window (CIW) input line:


```
setSkillPath(cons(prependInstallPath("samples/ROD/rodPcells")
    getSkillPath()))
load("install/spcLoadInstall.il")
spcInstall()
```

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---

The Welcome to the Sample Parameterized Cell Installation form appears. Read the form before continuing.




2. Click *Next*.

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---

The Load Devices form appears.



**Note:** Because some of these devices use CMOS technology and some bipolar, you cannot install all of the devices unless there are both CMOS and bipolar layers defined for your technology.

3. Choose the devices you want to install and click *Next*.

For more information on the devices, see [Chapter 2, “Sample Parameterized Cells Reference.”](#)

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---

The Select Destination Library form appears.



4. Choose a library from the *Available Libraries* cyclic field and click *Next*.

The SKILL code for the devices is loaded into the directory

`lib/examplePcellLib`

where `lib` is the path to the destination library you selected.

Only libraries that were created by compiling a technology file will be available for installing the sample Pcells.



## Sample Parameterized Cells Installation and Reference

### Overview and Installation

The Verify Layer Definitions form and the Define Layers form appear.

The image shows two overlapping dialog boxes. The background dialog is titled "Verify Layer Definitions" and contains instructions for verifying layer definitions. The foreground dialog is titled "Define Layers" and contains a table of layer definitions.

**Verify Layer Definitions Dialog:**

- Buttons: OK, Cancel, Previous, Next, Help
- Text: 3. Verify that all of the layer purpose pairs required by the sample pcells are defined in the Define Layers form.
- Instructions:
  - a. If a layer is undefined, or you want to change the value for a layer, click on the cyclic field associated with the layer.
  - b. Select the layer purpose pair appropriate for your technology.
  - c. When all layers are defined and you want to accept their values, click "OK".
- Text: Click on "Next" to continue.

**Define Layers Dialog:**

Layer Name	Layer Purpose Pair	Requirement
ndiff	ndiff dg	Required
nimplant	nimplant dg	Optional
pimplant	pimplant dg	Optional
metal1	metal1 dg	Required
base	base dg	Required
coll	undefined	Required
buried	buried dg	Required
iso	undefined	Required
cont	undefined	Required

There are three columns in the Define Layers form. The first lists the name of the layers used in the SKILL code for the devices, the second lists the corresponding layer-purpose pairs, and the third lists whether the layers are required or optional. A cyclic field labeled *undefined* identifies layers not previously defined in the technology file of the chosen

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---

library. You must define layer-purpose pairs for all required layers before continuing. You can also use this form to modify previously defined layers of the technology file. The following is a description of the layers used in the Pcell code.


<b>Pcell layer</b>	<b>Layer description</b>
capVia	Connects the capBot and capTop layers
capBot	Bottom layer of the capacitor
capTop	Top layer of the capacitor
nwell	n-type well layer
pwell	p-type well layer.
emit	Emitter layer of the npn device
iso	Isolation layer used on the npn, pnp and res devices
buried	Buried layer of the npn and pnp devices
coll	Collector layer of the npn device and the base layer of the pnp device
base	Base layer of the npn device and the collector and emitter layers of the pnp device
metal1	Metal layer
cont	Contact layer
pimplant	p-type implant layer
nimplant	n-type implant layer
ndiff	n-type diffusion layer
pdiff	p-type diffusion layer
poly	Polysilicon layer

5. Click the cyclic field to the right of the layer you want to define or modify.

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

A pop-up menu with several layer choices appears.



- Choose the layer-purpose pair that corresponds to the layers used in the Pcell code.
- Repeat for other layers as necessary.
- Click *OK* in the Define Layers form.

**Note:** If you did not select a layer-purpose pair for a required layer, an error message appears. Click *OK* in the dialog box and define all required layers in the Define Layers form.

- Click *Next* in the Verify Layer Definitions form.

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

The Verify Required Rules form and the Define Rules form appear.

The image shows two overlapping dialog boxes. The 'Verify Required Rules' dialog is in the background, and the 'Define Rules' dialog is in the foreground.

**Verify Required Rules Dialog:**

- Buttons: OK, Cancel, Previous, Next, Help
- Text: 4. Verify that all rules in the Define Rules form meet your specifications.
- Text: a. To change a rule, enter the new value to the right of the rule name.
- Text: b. When all rules are defined to your specifications, click "OK" in the Define Rules form.
- Text: Click on "Next" to continue.

**Define Rules Dialog:**

Rule Name	Value
minWidth poly	0.25
minGateSpacing poly	-1
minExtension poly	-1
minSpacing poly cont	-1
minSpacing poly pdiff	0.1
minSpacing poly ndiff	0.1
minSpacing metal1	0.35
minWidth metal1	0.35
minEnclosure ndiff poly	0.25

In the Define Rules form, any design rules that were not previously defined in the technology file default to -1.



**You must replace any -1 values with the correct design rule value. Values left at the default of -1 will prevent your technology file or your Pcell from evaluating.**

The rules in the Define Rules form and the values you assign to them are added to the techParams subclass of the controls class of the technology file. For more

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---

information on design rules and the technology file, refer to the [Technology File and Display Resource File User Guide](#).

7. Click in the field to the right of the rule you want to modify.
  - a. Type the correct design rule for your technology in the field.
  - b. Repeat for all design rules requiring modification.
  - c. Verify that there are no design rules with values of -1.
  - d. When you are finished, click *OK* in the Define Rules form.




**Caution**

***Modifying the rules changes the design rules saved to the technology file and affects all applications that use those rules.***

8. Click *Next* in the Verify Required Rules form.

The Verify Source Directory form appears.



In this form, you specify which directory contains the source files for the devices you want to install. By default, this is

`your_install_dir/tools/dfII/samples/ROD/rodPcells`

9. (Optional) If you have copied and modified the default source files, type the path to the modified files in the field, or click *Set Directory* to browse for the correct path.
10. Click *Next*.


## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---

**Note:** If you specified an invalid path, the Install Path Error dialog box appears. Click *OK* in the dialog box and specify a valid path.

The Loading Status form appears and confirms that the files for the devices you chose to install were found in the directory.




11. Click *Next*.

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---

The Initialization Choices form appears.



In this form, you choose where to include instructions for loading the Cadence SKILL language files defining the devices.

☒ *libInit*

Choosing `libInit.il` creates a file in the library directory or adds additional information to an existing `libInit.il` file. All applications read the `libInit.il` file, which enables all applications and environments to evaluate the sample Pcells. For more information about the `libInit.il` file, refer to [“Loading Pcells from the libInit.il File”](#) on page 25.

☐ *cdsinit*

Choosing `.cdsinit` creates a file in the library directory, or adds additional information to an existing `.cdsinit` file. When loading Pcells from the `.cdsinit` file, the sample Pcells are loaded when you start the software.

Not all applications read the `.cdsinit` file. Sample Pcells will not be evaluated for translation in background mode by applications that do not use the `.cdsinit` file. For any background translation that does not use the `.cdsinit` file, you need to explicitly load the SKILL code for the devices.

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---

#### ❑ *none*

Choosing none requires you to load the SKILL files manually before the system can evaluate your Pcells. The following example loads the *bentmos* sample Pcell.

```
load(strcat(ddGetObjReadPath(ddGetObj("RODpcells"))
"/examplePcellLib/spcLoadUtilities.il"))
load(strcat(ddGetObjReadPath(ddGetObj("RODpcells"))
"/examplePcellLib/utility.il"))
load(strcat(ddGetObjReadPath(ddGetObj("RODpcells"))
"/examplePcellLib/bentmos.callback"))
load(strcat(ddGetObjReadPath(ddGetObj("RODpcells"))
"/examplePcellLib/bentmos.il"))
```

**Note:** To load Pcells for background translation using XStream, use the *User SKILL File*. For more information, refer to [“Design Translation Using XStream translator”](#) in the *Design Data Translator’s Reference on OpenAccess*.

#### 12. Make a selection and click *Next*.

The Installation Completed form and the Save Technology File form appear.



The changes you make to the layer definitions and design rules during this installation session override any previous changes you made to the technology file.




## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---

13. In the Save Technology File form, click *OK* to save your changes to the library shown in the cyclic field.

A confirmation dialog appears.



14. In the confirmation dialog, click *Yes*.

The installation is complete.

15. Click *OK* to exit the installation utility.

## Validating the Installation

To validate the installation of the sample cells, follow these steps:

1. Open the Library Browser and verify that the new device masters exist in the destination library.
2. Place each of the devices in a new layout view and verify that they are created properly.
3. If you were prompted to save your technology file, exit and then restart the Cadence software to verify that the modified technology file and the `libInit.il` or `.cdsinit` files load correctly.

## Loading Pcells from the libInit.il File

When loading Pcells from the `libInit.il` file, the system loads the sample Pcells when the library is accessed (the first time a cellview is opened). If the sample Pcells are loaded into multiple libraries and from your `libInit.il`, the first time each of the libraries in which the sample Pcells have been installed is accessed, the Pcells will be evaluated. This causes multiple messages about redefined functions to appear in the CIW. These redefined messages can safely be ignored. To avoid multiple redefined messages, you can add

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---

additional SKILL code to your `libInit.il` files. The following example adds an `unless(boundp( 'SPCLOADED))` statement before the first line of code that was added by the installation program and sets the global variable `SPCLOADED` to `t` after the last device load call.

```
unless( boundp( 'SPCLOADED) ; Adds global variable and checks if bound.
load(strcat(ddGetObjReadPath(ddGetObj("designLib"))
"/examplePcellLib/spcLoadUtilities.il"))
load(strcat(ddGetObjReadPath(ddGetObj("designLib"))
"/examplePcellLib/utility.il"))
load(strcat(ddGetObjReadPath(ddGetObj("designLib"))
"/examplePcellLib/mos.il"))
load(strcat(ddGetObjReadPath(ddGetObj("designLib"))
"/examplePcellLib/mos.callback"))
SPCLOADED = t
); Sets the global variable to true if Pcells are loaded.
```

The use of the `libInit.il` file has some restrictions. SKILL code loaded by the `libInit.il` file should only assume that low-level SKILL functions are available, such as those permitted in parameterized cells. When you use SKILL routines within `libInit.il`, use only the following functions:

- The SKILL functions documented in the SKILL Language Reference Manual; for example: `car`, `if`, `foreach`, `sprintf`, `while`.
- SKILL functions from the following families: `db` `dd` `cdf` `rod` `tech`

No SKILL code loaded by the `libInit.il` file should be dependent on graphical SKILL functions like `hiSetBindKey`.

To call functions or load files that use graphical SKILL functions, for example, from the `hi`, `ge`, `le`, `sch` families, make the code conditional with `isCallable`.

For example:

```
if(isCallable('hiSetBindKey)
    hiSetBindKey(....)
    ...
)
```

## Modifications Made to the Technology File

The installation script makes several modifications to your technology file.

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---

### Layer Correspondence Parameters in techParams

The installation script creates a table in the `techParams` subclass that lists the generic layer functions used in the parameterized cells and the corresponding layer numbers in your particular technology. You define this data when you fill in the Define Layers form.

**Note:** The `techParams` subclass may also contain router translation rules that are unrelated to these sample parameterized cells.

Below is an example of this table of parameters and values.

```
; ( parameter          value          )
; ( -----          -)
; ( poly              ("poly1" "drawing") )
; ( metall            ("metall" "drawing") )
; ( cont              ("contact" "drawing") )
; ( nimplant          ("txtndiff" "drawing") )
; ( pimplant          ("txtpdiff" "drawing") )
; ( ndiff             ("ndiff" "drawing") )
; ( pdiff             ("pdiff" "drawing") )
; ( nwell             ("nwell" "drawing") )
; ( pwell             ("viaE" "drawing") )
```

The `techParams` subclass also receives several variables that define characteristics of the sample devices:

This Variable...	Is Used in This Cell...
minMosWidth	spcnmos, spcpmos
minRes	spcres
emitArea, emitBaseSpacing	spcnpn
minCap, capCoeff, unitC, maxCap	spccap

### Physical DRC Rules

The `minEnclosure`, `minSpacing`, and `minWidth` rules in the `physicalRules` section of the technology file are used to set default values in the Define Rules form. The installation script adds additional rules to the `physicalRules` section for any design rules that were not previously defined in the technology file. These rules are shared by other Cadence design framework II applications.

## Sample Parameterized Cells Installation and Reference

### Overview and Installation

---



**Caution**

***If you modify the rules while installing the cells, you affect all applications that use the rules.***

## Device Classes

In the `devices` section of the technology file, the installation script creates device classes for each cell. The class for the `spcbentnmos` and `spcbentpmos` devices is `syBGEenhancement`. The classes for the other devices begin with the prefix `spc` and follow the naming of the devices themselves. For example:

```
tcCreateDeviceClass( "layout" "spcsimple_mos" )
```

During the installation script, you are prompted to install SKILL functions for the cells in the `libInit.il` file (or in your `.cdsinit` file). The device classes in the technology file call these SKILL functions.

---

## Sample Parameterized Cells Reference

---

This chapter discusses the following:

- [Modifying Pcell Parameter Values](#) on page 29
- [spcbentnmos, spcbentpmos](#) on page 30
- [spccap](#) on page 32
- [spcinv](#) on page 35
- [spcnmos, spcpmos](#) [on page 37](#)
- [spcnpn](#) on page 41
- [spcpnp](#) on page 42
- [spcpres](#) on page 44
- [spcres](#) on page 46
- [spcsimple\\_nmos, spcsimple\\_pmos](#) on page 49

### Modifying Pcell Parameter Values

Once you have installed the sample Pcells, you can place instances of them in your layout and modify their parameters to suit your specifications. When you place an instance using the Create Instance form (choose *Create – Instance*), the system prompts you to enter values for a variety of parameters or to accept the defaults. You can modify an instance using the Edit Properties form (choose *Edit – Properties*) as well.

Each section in this chapter consists of a brief discussion of a sample Pcell and a description of its parameters as they appear in the Create Instance and Edit Properties forms. Each parameter entry contains information about the purpose and default value of the parameter. When appropriate, some entries also provide information about valid parameter values and examples of such values.

## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### Default Values

During the installation, you assigned values to design rules and then saved them to the `techParams` subclass of the `controls` class of the technology file. The default values for many of the parameters of the sample Pcells are derived from these same values.


For instance, the gate length of the `spcbentnmos` device defaults to the minimum width of the poly layer (`minWidth poly`), which you specified during the installation. The values that you can specify for many of the parameters are bounded by these same technology file values.

#### spcbentnmos, spcbentpmos

The `spcbentnmos` device is an NMOS transistor with a bent-gate option, and the `spcbentpmos` device is the PMOS equivalent. The parameter *Coordinate list* allows you to modify the path of the gate by specifying the coordinates of the center of the gate.

This section discusses the `spcbentnmos`/`spcbentpmos` device parameters that appear in the Create Instance (choose *Create – Instance*) and Edit Properties (choose *Edit – Properties*) forms of the Virtuoso® layout editor. The default values for many of the parameters come from your technology file.

#### The spcbentpmos Device, Placed with Source and Drain Contacts, and Coordinate List Set to (0.0:0.0 10.0:0.0 10.0:3.0 20.0:3.0)



## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### Parameters

<i>Gate Width</i>	<p>Controls the width of the gate. When <i>Coordinate list</i> has values specified, <i>Gate Width</i> is derived from those values.</p> <p>Valid Values: a number in meters, in engineering notation, greater than or equal to the value of <code>minMosWidth</code></p> <p>Example: <code>4e-6</code></p> <p>Default: the value of <code>minMosWidth</code></p>
<i>Gate Length</i>	<p>Controls the length of the gate.</p> <p>Valid Values: a number in meters, in engineering notation, greater than or equal to the value of <code>minWidth poly</code></p> <p>Example: <code>6e-7</code></p> <p>Default: the value of <code>minWidth poly</code></p>
<i>Multiplication Factor</i>	<p>The Virtuoso layout accelerator (Virtuoso XL) supports the use of the <u>multiplication factor</u> (m-factor) as a parameter to define a one-to-many parallel relationship between a device in a schematic and multiple instances of the device in the layout. This parameter is intended for use at the schematic level; if you change the m-factor of a layout view, the system multiplies the width of the device by the specified factor.</p> <p>Valid Values: a positive floating-point number</p> <p>Default: 1</p>
<i>Coordinate list</i>	<p>Defines the X and Y coordinates of the gate path.</p> <p>Valid Values: a list of X:Y coordinates</p> <p>Example: <code>(0.0:0.0 10.0:0.0 10.0:3.0 20.0:3.0)</code></p> <p>Default: none (the gate is straight)</p>
<i>Source Contacts?</i>	<p>Adds source contacts. The <i>Source Contact Position</i> and <i>Source Contact Coverage</i> parameters appear when <i>Source Contacts?</i> is on.</p> <p>Default: off</p>
<i>Drain Contacts?</i>	<p>Adds drain contacts. The <i>Drain Contact Position</i> and <i>Drain Contact Coverage</i> parameters appear when <i>Drain Contacts?</i> is on.</p> <p>Default: off</p>

## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### *Source Contact Position*

Positions the contacts vertically within the source. When the contacts are not spread out evenly along the width of the source, you can shift the contacts toward the top, center, or bottom of the source, relative to the unrotated device.

Valid Values: *Center*, *Top*, or *Bottom*

Default: *Center*

*Drain Contact Position* Positions the contacts vertically within the drain. When the contacts are not spread out evenly along the width of the drain, you can shift the contacts toward the top, center, or bottom of the drain, relative to the unrotated device.

Valid Values: *Center*, *Top*, or *Bottom*

Default: *Center*

#### *Source Contact Coverage*

Controls the percentage of the width of the source that the contacts cover. This lets you route other metal lines across the device without connecting them to it electrically.

Valid Values: 10 to 100

Default: 100

#### *Drain Contact Coverage*

Controls the percentage of the width of the drain that the contacts cover. This lets you route other metal lines across the device without connecting them to it electrically.

Valid Values: 10 to 100

Default: 100

#### *Bulk Node Connection(s)*

Connects the bulk-substrate to source or drain.

Valid Values: *S* for source, *D* for drain, or blank for neither

Default: *S*

## **spccap**

The spccap device is an array capacitor. You can change the aspect ratio of the array by adjusting the number of rows and columns. You can round up the unit capacitance value or add an extra capacitor to the array to achieve the precise required capacitance value.

This section discusses the spccap device parameters that appear in the Create Instance (choose Create – Instance) and Edit Properties (choose Edit – Properties) forms of the




## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

Virtuoso layout editor. The default values for many of the parameters come from your technology file.

#### The spccap Device, Placed in a Four-Column Array Layout



## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### Parameters

<i>Capacitance</i>	<p>Controls the required capacitance.</p> <p>Valid Values: a number in farads, in engineering notation, greater than or equal to the value of <code>minCap</code> and less than or equal to the value of <code>maxCap</code></p> <p>Example: <code>1e-4</code></p> <p>Default: the value of <code>minCap</code></p>
<i>Actual Capacitance</i>	<p>Specifies the total capacitance of all the unit capacitors in the Pcell. This is a noneditable field.</p>
<i>Array Type Layout?</i>	<p>Builds the Pcell of multiple-unit capacitor tiles.</p> <p>Default: on</p>
<i>Connect Capacitor Tiles</i>	<p>Connects the unit capacitors within the Pcell.</p> <p>Default: off</p>
<i>Define Array By</i>	<p>Controls the internal layout of multiple-unit capacitors within the Pcell.</p> <p>Valid Values: <i>Square</i>, <i>Rows</i>, or <i>Columns</i></p> <p>Default: <i>Square</i></p>
<i>Number of Rows</i>	<p>Controls the number of rows of unit capacitors within the Pcell.</p> <p>Valid Values: a positive integer</p> <p>Default: 1</p>
<i>Number of Columns</i>	<p>Controls the number of columns of unit capacitors within the Pcell.</p> <p>Valid Values: a positive integer</p> <p>Default: 1</p>
<i>Unit Size Capacitance</i>	<p>Controls the required capacitance for the unit capacitors within the Pcell.</p> <p>Valid Values: a number in farads, in engineering notation</p> <p>Default: the value of <code>unitC</code></p>
<i>Cap Round Up?</i>	<p>Rounds the capacitance value to the next higher unit of capacitance. <i>Cap Round Up?</i> and <i>Add Extra</i> cannot both be on at the same time.</p> <p>Default: on</p>

## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### *Add Extra*

Adds an extra capacitor to achieve the required capacitance. *Add Extra* and *Cap Round Up?* cannot both be on at the same time.

Default: off

#### *Multiplication Factor(m)*


Virtuoso XL supports the use of the multiplication factor (m-factor) as a parameter to define a one-to-many parallel relationship between a device in a schematic and multiple instances of the device in the layout. This parameter is intended for use at the schematic level.

## spcinv

The spcinv device is an inverter built using the spcnmos and the spcpmos devices. You can modify the gate width and length of both transistors, define the supply width, and set the height of the whole cell. Note the stretch handles that let you graphically scale the device.

This section discusses the spcinv device parameters that appear in the Create Instance (choose Create – Instance) and Edit Properties (choose Edit – Properties) forms of the Virtuoso layout editor. The default values for many of the parameters come from your technology file.

### The spcinv Device, Placed with 90° of Rotation



## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### Parameters

<i>nMos Gate Width</i>	<p>Controls the width of the gate of the NMOS transistor in the inverter.</p> <p>Valid Values: a number in meters, in engineering notation Example: 3e-6 Default: the value of <code>minMosWidth ndiff</code></p>
<i>nMos Gate Length</i>	<p>Controls the length of the gate of the NMOS transistor in the inverter.</p> <p>Valid Values: a number in meters, in engineering notation Example: 1e-7 Default: the value of <code>minWidth poly</code></p>
<i>nMos fingers</i>	<p>Controls the number of fingers in the NMOS transistor.</p> <p>Valid Values: a positive integer Default: 1</p>
<i>pMos Gate Width</i>	<p>Controls the width of the gate of the PMOS transistor in the inverter.</p> <p>Valid Values: a number in meters, in engineering notation Example: 4e-6 Default: the value of <code>minMosWidth pdiff</code></p>
<i>pMos Gate Length</i>	<p>Controls the length of the gate of the PMOS transistor in the inverter.</p> <p>Valid Values: a number in meters, in engineering notation Example: 1e-7 Default: the value of <code>minWidth poly</code></p>
<i>pMos fingers</i>	<p>Controls the number of fingers in the PMOS transistor.</p> <p>Valid Values: a positive integer Default: 1</p>
<i>Supply Width</i>	<p>Controls the width of the power and ground lines.</p> <p>Valid Values: a number in meters, in engineering notation Example: 2.4e-6 Default: the value of <code>minWidth metall * 3</code></p>
<i>Cell Height</i>	<p>Controls the distance from the bottom of the ground supply to the top of the power supply.</p> <p>Valid Values: a number in meters, in engineering notation Example: 2.2e-5 Default: the value of <code>minWidth metall * 30</code></p>

## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### *Add substrate contacts?*

Adds substrate contacts.

Default: on

#### *Cell Horiz. Pitch*

Controls the length of device. The system modifies the length of the supply lines to be a multiple of the cell horizontal pitch value.

Valid Values: a number in meters, in engineering notation

Example: 5e-8

Default: the value of `mfgGridResolution`

## spcnmos, spcpmos

The spcnmos device is an n-diffusion straight-gate MOS transistor, and the spcpmos device is the p-diffusion equivalent. You can modify the gate width and length of the transistor, apply fingered or threshold gate splitting, add contacts to either side of the gate, and specify the position of the source and drain contacts.


This section discusses the spcnmos/spcpmos device parameters that appear in the Create Instance (choose Create – Instance) and Edit Properties (choose Edit – Properties) forms of the Virtuoso layout editor. The default values for many of the parameters come from your technology file.

## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

**The spcnmos Device, Placed with Left, Right, and Substrate Contacts and a Four-Fingered Split Gate**



## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### Parameters

<i>Gate Width</i>	<p>Controls the width of the gate.</p> <p>Valid Values: a number in meters, in engineering notation, greater than or equal to the value of <code>minMosWidth</code></p> <p>Example: <code>4e-6</code></p> <p>Default: the value of <code>minMosWidth</code></p>
<i>Gate Length</i>	<p>Controls the length of the gate.</p> <p>Valid Values: a number in meters, in engineering notation, greater than or equal to the value of <code>minWidth poly</code></p> <p>Example: <code>1e-6</code></p> <p>Default: the value of <code>minWidth poly</code></p>
<i>Multiplication Factor(m)</i>	<p>Virtuoso XL supports the use of the <u>multiplication factor</u> (m-factor) as a parameter to define a one-to-many parallel relationship between a device in a schematic and multiple instances of the device in the layout. This parameter is intended for use at the schematic level; if you change the m-factor of a layout view, the system multiplies the width of the device by the specified factor.</p> <p>Valid Values: a positive floating-point number</p> <p>Default: 1</p>
<i>Gate Splitting</i>	<p>Splits the gate. The <i>Type of Splitting</i>, <i>Number of Fingers</i> (or <i>Threshold Value</i> if <i>Type of Splitting</i> is set to <i>Threshold</i>), and <i>Internally connect poly?</i> parameters appear when <i>Gate Splitting</i> is on.</p> <p>Default: off</p>
<i>Type of Splitting</i>	<p>Controls how the gate is split.</p> <p>Valid Values: <i>Fingered</i> or <i>Threshold</i></p> <p>Default: <i>Fingered</i></p>
<i>Number of Fingers</i>	<p>Controls the number of fingers in the transistor.</p> <p>Valid Values: a positive integer</p> <p>Default: 1</p>
<i>Threshold Value</i>	<p>Specifies the maximum width for each gate when <i>Gate Splitting</i> is on.</p> <p>Valid Values: a number in meters, in engineering notation, greater than or equal to the value of <code>minMosWidth * 10</code></p> <p>Example: <code>30</code></p> <p>Default: the value of <code>minMosWidth * 10</code></p>

## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

<i>Left Contacts</i>	Adds contacts to the left of each gate relative to the unrotated device. The left contact is always the source contact. If you set <i>Number of Fingers</i> to an even number, the source contacts and drain contacts alternate, starting with a source contact to the left of the left-most gate (relative to the unrotated device). Default: on
<i>Right Contacts</i>	Adds contacts to the right of each gate relative to the unrotated device. If you set <i>Number of Fingers</i> to an odd number, the right contact is a drain. If you set <i>Number of Fingers</i> to an even number, the source contacts and drain contacts alternate, starting with a source contact to the left of the left-most gate (relative to the unrotated device). Default: on
<i>Add substrate contact?</i>	Adds substrate contacts. The <i>Substrate Contact Position</i> parameter appears when <i>Add substrate contact?</i> is on. If <i>Bulk Node Connection</i> is set to <i>S</i> , the substrate contact is positioned to the left of the gate, relative to the unrotated device. If <i>Bulk Node Connection</i> is set to <i>D</i> , the substrate contact is positioned to the right of the gate, relative to the unrotated device. Default: off
<i>Substrate Contact Position</i>	Positions the substrate contact relative to the unrotated device. Valid Values: <i>Top</i> or <i>Bottom</i> Default: <i>Top</i>
<i>Add substrate well?</i>	Adds a substrate well. Default: off
<i>Bulk Node Connection</i>	Connects the bulk substrate to the source or drain. Valid Values: <i>S</i> for source, <i>D</i> for drain, or blank for neither Default: <i>S</i>
<i>Internally connect poly?</i>	Connects the poly gates to each other within the Pcell. Default: off
<i>Connect poly</i>	Positions the poly gate connection relative to the unrotated device. Valid Values: <i>Top</i> or <i>Bottom</i> Default: <i>Top</i>



## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---


*Connect S/D to metal?* Connects the source or the drain to metal.  
Valid Values: *None*, *Source*, *Drain*, or *Source&Drain*  
Default: *None*

## spcnpn

The spcnpn device is an NPN bipolar transistor that, given the wide variety of bipolar transistor designs, has been kept fairly simple. There are five choices of collector, emitter, and base configurations and a parameter for the emitter width. Note the stretch handles that let you graphically scale the device.

This section discusses the spcnpn device parameters that appear in the Create Instance (choose *Create – Instance*) and Edit Properties (choose *Edit – Properties*) forms of the Virtuoso layout editor. The default values for many of the parameters come from your technology file.

### The spcnpn Device, Placed in the CBE Configuration



## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### Parameters

<i>NPN Type</i>	Chooses the collector-base-emitter configuration. Valid Values: <i>CBE</i> , <i>CEB</i> , <i>CEBC</i> , <i>CBEC</i> , or <i>CEBEC</i> Default: <i>CBE</i>
<i>Emitter Width</i>	Controls the width of the emitter. Valid Values: a number in meters, in engineering notation Example: 2.6e-6 Default: the value of 2 * (2 * minEnclosure emit cont + minWidth cont)
<i>Multiplication Factor</i>	Virtuoso XL supports the use of the <u>multiplication factor</u> (m-factor) as a parameter to define a one-to-many parallel relationship between a device in a schematic and multiple instances of the device in the layout. This parameter is intended for use at the schematic level.

## spcpnp

The spcpnp device is a stretchable PNP bipolar transistor that, given the wide variety of bipolar transistor designs, has been kept fairly simple. The Pcell contains the emitter and the base. The collector is a zero-level multipart path built with the ROD function rodCreatePath.


This section discusses the spcpnp device parameters that appear in the Create Instance (choose Create – Instance) and Edit Properties (choose Edit – Properties) forms of the Virtuoso layout editor. The default values for many of the parameters come from your technology file.

## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### The spcpnp Device



## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### Parameters

<i>P+ Emitter Width</i>	Controls the width of the gate.  Valid Values: a number in meters, in engineering notation Example: 6e-6 Default: the value of $2 * (2 * \text{minEnclosure base cont} + \text{minWidth cont})$
<i>Multiple emitters</i>	Controls the number of emitters in the Pcell. Valid Values: a positive integer Default: 1
<i>Emitter access direction</i>	Selects the access direction of the emitter. Valid Values: <i>Top, Left, Right, Bottom, or None.</i> Default: <i>Top</i>
<i>Multiplication Factor</i>	Virtuoso XL supports the use of the <u>multiplication factor</u> (m-factor) as a parameter to define a one-to-many parallel relationship between a device in a schematic and multiple instances of the device in the layout. This parameter is intended for use at the schematic level.

## spcpres

Sometimes resistors in a schematic represent estimates of the resistance that certain signals might have after the layout designer draws the design. Including these resistors helps improve the simulation results. During layout, the designer does not draw the resistor because it represents the resistance of the shapes needed to connect the other components.

Virtuoso XL expects the layout to match the schematic device for device and net for net. The spcpres device was designed to let you place a resistor in the schematic and connect separate nets to each side of the device, without causing Virtuoso XL to expect to see a corresponding resistor in the layout.


The spcpres device uses the sheet resistance (`sheetRes`) from the technology file for the metal layer and adjusts the device size accordingly. Given the low resistance of the metal layer, you need to enter relatively large values to see a visible change in the layout view. The pins are never placed more than twice the minimum grid spacing apart. The separation between the pins prevents the Virtuoso XL connectivity extractor from reporting a short where the two nets touch. Note the stretch handles that let you graphically scale the device.

## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### The spcpres Device



## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### Parameters

<i>Resistor type</i>	Selects the type of resistor material.  Valid Values: <i>poly</i> , <i>ndiff</i> , <i>pdiff</i> , or <i>metal1</i> Default: <i>metal1</i>
<i>Input value</i>	Specifies the input that defines the resistor. Valid Values: <i>Length</i> or <i>Resistance</i> Default: <i>Resistance</i>
<i>Resistance</i>	Controls the total resistance of the device. Valid Values: a number in ohms, in engineering notation Example: 8e+3 Default: the value of 8 * minRes
<i>Length</i>	Controls the length of the resistor path. Valid Values: a number in meters, in engineering notation Default: varies based on the values of minRes and the values of sheetRes and minWidth of the specified resistor type.
<i>Width</i>	Controls the width of the resistor path. Valid Values: a number in meters, in engineering notation Default: the value of minWidth for the resistive layer
<i>Multiplication Factor</i>	Virtuoso XL supports the use of the <u>multiplication factor</u> (m-factor) as a parameter to define a one-to-many parallel relationship between a device in a schematic and multiple instances of the device in the layout. This parameter is intended for use at the schematic level. Default: 1

## spcres

The spcres device is a resistor built to let you define the type of resistor material (poly, n-diffusion, or p-diffusion), resistance, length, and width. You can draw the resistor in a serpentine or strap formation for layout optimization.

This section discusses the spcres device parameters that appear in the Create Instance (choose Create – Instance) and Edit Properties (choose Edit – Properties) forms of the Virtuoso layout editor. The default values for many of the parameters come from your technology file.



## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### Parameters

<i>Resistor type</i>	Selects the type of resistor material.  Valid Values: <i>poly</i> , <i>ndiff</i> , or <i>pdiff</i> Default: <i>poly</i>
<i>Resistance</i>	Controls the total resistance of the device. Valid Values: a number in ohms, in engineering notation Example: 8e+3 Default: the value of 8 * minRes
<i>Length</i>	Controls the length of the resistor path. Valid Values: a number in meters, in engineering notation Default: varies based on the values of minRes and the values of sheetRes and minWidth of the specified resistor type.
<i>Input value</i>	Specifies the input that defines the resistor. Valid Values: <i>Length</i> or <i>Resistance</i> Default: <i>Resistance</i>
<i>Width</i>	Controls the width of the resistor path. Valid Values: a number in meters, in engineering notation Default: the value of minWidth poly
<i>Draw resistor as</i>	Selects the shape of the resistor. Choose <i>Straps</i> to draw the resistor with the number of resistor paths specified in <i>Number of segments</i> between the contacts. Choose <i>Serpentine</i> to draw the resistor path in an accordion shape with the specified number of segments. Examples: If you choose <i>Straps</i> and set <i>Number of segments</i> to 5, the total resistor value is split evenly among five individual resistors, which are connected in series. If you choose <i>Serpentine</i> and set <i>Number of segments</i> to 5, the system draws a single, five-segment, accordion-shaped resistor. Valid Values: <i>Straps</i> or <i>Serpentine</i> Default: <i>Straps</i>



## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

<i>Number of segments</i>	Controls the number of straps or serpentine segments. When you set <i>Draw resistor as</i> to <i>Straps</i> , <i>Number of segments</i> controls how many resistor paths the system draws between the serially connected contacts. When you set <i>Draw resistor as</i> to <i>Serpentine</i> , <i>Number of segments</i> controls how many segments are in the accordion shape of the resistor path. Valid Values: an integer, with a minimum value of 1 for straps and 2 for serpentine Default: 1
<i>Serpentine width</i>	Controls the width of the serpentine resistor path. Valid Values: a number in meters, in engineering notation Default: varies based on the values of <code>minWidth cont</code> , <code>minEnclosure metall cont</code> , and the <code>minSpacing</code> and <code>minWidth</code> values of the specified resistor type.
<i>Multiplication Factor</i>	Virtuoso XL supports the use of the <u>multiplication factor</u> (m-factor) as a parameter to define a one-to-many parallel relationship between a device in a schematic and multiple instances of the device in the layout. This parameter is intended for use at the schematic level.

## spcsimple\_nmos, spcsimple\_pmos

The `spcsimple_nmos` and `spcsimple_pmos` devices are simpler implementations of transistors than the `spcnmos` and `spcpmos` devices.

These simpler devices do not support wells and substrate contacts, and the contact choices are more limited. The contact coverage and the choice to have contacts are merged into a single contact coverage parameter, which is set in a cyclic field.

The splitting variable in the `spcnmos` and `spcpmos` devices that later prompts you for the number of fingers was replaced with a single parameter in the `spcsimple_nmos` and `spcsimple_pmos` devices. Any value larger than 1 in the *Number of Fingers* field splits the device. There is no choice of types of splitting. Note the stretch handles that let you graphically scale the device.


These devices support relative object design (ROD) commands, Virtuoso XL permutable pins and device abutment, and pin connection modeling (strong, weak, and must-join) for the Virtuoso custom router. These devices are not compatible with the Virtuoso compactor or the Virtuoso layout synthesizer.

## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### The spcsimple\_nmos Device



## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

#### Parameters

<i>Gate Width</i>	<p>Controls the width of the gate.</p> <p>Valid Values: a number in meters, in engineering notation, greater than or equal to the value of <code>minMosWidth</code></p> <p>Example: <code>4e-6</code></p> <p>Default: the value of <code>minMosWidth</code></p>
<i>Gate Length</i>	<p>Controls the length of the gate.</p> <p>Valid Values: a number in meters, in engineering notation, greater than or equal to the value of <code>minWidth poly</code></p> <p>Example: <code>1e-6</code></p> <p>Default: the value of <code>minWidth poly</code></p>
<i>Multiplication Factor(m)</i>	<p>Virtuoso XL supports the use of the <u>multiplication factor</u> (m-factor) as a parameter to define a one-to-many parallel relationship between a device in a schematic and multiple instances of the device in the layout. This parameter is intended for use at the schematic level; however, if you change the m-factor of a layout view, the system multiplies the width of the device by the specified factor.</p> <p>Valid Values: a positive floating-point number</p> <p>Default: 1</p>
<i>Number of Fingers</i>	<p>Controls the number of fingers in the transistor.</p> <p>Valid Values: a positive integer</p> <p>Default: 1</p>
<i>Threshold Value</i>	<p>Specifies the maximum width for each gate when <i>Number of Fingers</i> is greater than 1.</p> <p>Valid Values: a number in meters, in engineering notation, greater than the value of <code>minMosWidth * 10</code></p> <p>Example: <code>30</code></p> <p>Default: <code>0.0</code></p>
<i>Left Contact Position</i>	<p>Positions the contacts vertically. When the contacts are not spread out evenly along the width of the drain, you can shift the contacts toward the top, center, or bottom of the drain, relative to the unrotated device.</p> <p>Valid Values: <i>Center</i>, <i>Top</i>, or <i>Bottom</i></p> <p>Default: <i>Center</i></p>

## Sample Parameterized Cells Installation and Reference

### Sample Parameterized Cells Reference

---

*Left Contact Coverage* Controls the percentage of the width of the left side of the device that the contacts cover. This lets you route other metal lines across the device without connecting them to it electrically.  
Valid Values: 0, 25, 50, 75, or 100  
Default: 100

*Right Contact Position* Positions the contacts vertically. When the contacts are not spread out evenly along the width of the drain, you can shift the contacts toward the top, center, or bottom of the drain, relative to the unrotated device.  
Valid Values: *Center*, *Top*, or *Bottom*  
Default: *Center*

*Right Contact Coverage*  
Controls the percentage of the width of the device that the right side contacts cover. This lets you route other metal lines across the device without connecting them to it electrically.  
Valid Values: 0, 25, 50, 75, or 100  
Default: 100

*Center Contact Position*  
Positions the center contact, if there is more than one finger.  
Valid Values: *Center*, *Top*, or *Bottom*  
Default: *Center*

*Center Contact Coverage*  
Controls the right side contacts coverage, if there is more than one finger. This lets you route other metal lines across the device without connecting them to it electrically.  
Valid Values: 0, 25, 50, 75, or 100  
Default: 100

---

## Building Pcells with ROD Functions

---

The Pcells described in this reference were built in part with relative object design functions (ROD), a set of high-level Cadence® SKILL language functions for defining simple and complex layout objects and their relationships to each other. The following code examples demonstrate how to use ROD functions to build Pcells.

**Note:** If you want to make changes to the code in any of the Pcell devices, utility functions, or installation files, you should create a copy of the original sample file using a new filename and make your changes to the new file. This method preserves the sample files for future use. If you do not create new files when you customize, your custom files replace the original sample files, and when the sample Pcells are loaded again, your custom files are overwritten by the original sample files.

### Multipart Paths, Subpaths, and Subrectangles

This code example utilizes the ROD function rodCreatePath to create a guardring consisting of an enclosure subpath and a subrectangle.

```
procedure(buildGuardRing(cv layer1 layer2 layer3 width1 width3
    length3 pathpnts terminal pinlabel enc offset chop)

; pinlabel is a boolean that determines whether a label will be
  created

  let(( guardRing )
    guardRing = rodCreatePath(
      ?cvId cv
      ?layer layer1
      ?width width1
      ?pts pathpnts
      ?encSubPath list( list(
        ?layer layer2
        ?enclosure enc
        ?choppable chop
        ?pin t
        ?termName terminal
        ?pinLabel pinlabel
        ?pinLabelHeight length3
        ?pinLabelLayer "text"
      ))
      ?subRect list( list(
```

## Sample Parameterized Cells Installation and Reference

### Building Pcells with ROD Functions

---

```
        ?layer layer3
        ?width width3
        ?length length3
        ?endOffset offset
    ))
)
))
```

## Path Stitching with ROD Functions

This code example uses the ROD functions [rodAlign](#) and [rodCreateRect](#) to build a Pcell that can be used for path stitching. It is set up for double contacts.

To use this example,

1. Copy the sample `mpu.tf` from

`your_install_dir/tools/dfII/samples/techfiles/mpu.tf`

to the location where you store your libraries.

2. Comment out `M1_POLY1` from the `device` class of the technology file.

This is necessary because path stitching will see two contact definitions for the same layer and choose the single-contact definition

3. Create a new technology library using `mpu.tf` as the ASCII technology file.
4. Load this file into your new library.

You can now use double contacts for path stitching.

```
; Path Stitching Example
devices(
tcCreateDeviceClass( "symbolic" "syEnhContact"
    ; class parameters
    ( (viaLayer "cont")
      (viaPurpose "drawing")
      (layer1 "poly1")
      (purpose1 "drawing")
      (layer2 "metall1")
      (purpose2 "drawing")
      (encByLayer1 .4)
      (encByLayer2 .6)
    )
    ; formal parameters
    ( (w 1.8)
      (l .6)
      (row 1)
      (column 1)
      (xPitch 2.4)
      (yPitch 1.2)
      (xBias "center")
      (yBias "center")
    )
  )
)
```

## Sample Parameterized Cells Installation and Reference

### Building Pcells with ROD Functions

---

```
)
cw = .6
cs = .6
lay1 = rodCreateRect(
    ?layer list(layer1 purpose1)
    ?width 2 * encByLayer1 + column * w + (column - 1) * cs
    ?length 2 * encByLayer1 + row * l + (row - 1) * cs
    ?pin t
    ?termName "mlp"
)
lay2 = rodCreateRect(
    ?layer list(layer2 purpose2)
    ?width 2 * encByLayer2 + column * w + (column - 1) * cs
    ?length 2 * encByLayer2 + row * l + (row - 1) * cs
    ?pin t
    ?termName "mlp"
)
for(i 0 row - 1
    yStep = i * yPitch
    for(j 0 column - 1
        contlay1 = rodCreateRect(
            ?layer list(viaLayer viaPurpose)
            ?width cw
            ?length cw
        )
        contlay2 = rodCreateRect(
            ?layer list(viaLayer viaPurpose)
            ?width cw
            ?length cw
        )
        rodAlign(
            ?alignObj contlay1
            ?alignHandle "cC"
            ?refObj lay1
            ?refHandle "lL"
            ?xSep encByLayer1 + cw/2 + j * xPitch
            ?ySep encByLayer1 + cw/2 + yStep
        )
        rodAlign(
            ?alignObj contlay2
            ?alignHandle "cC"
            ?refObj lay1
            ?refHandle "lL"
            ?xSep encByLayer1 + cw/2 + j * xPitch + yPitch
            ?ySep encByLayer1 + cw/2 + yStep
        )
    )
)
rodAlign(
    ?alignObj lay1
    ?alignHandle "centerCenter"
    ?refObj lay2
    ?refHandle "cC"
)
)
tfcDefineDeviceClassProp(
; (viewName      devClassName      propName      propValue)
  (symbolic      syEnhContact      function      "contact")
)
tcDeclareDevice( "symbolic" "syEnhContact" "M1_PLY"
    ( (viaLayer "cont") (viaPurpose "drawing")
```

## Sample Parameterized Cells Installation and Reference

### Building Pcells with ROD Functions

---

```
(layer1 "poly1") (purpose1 "drawing")
(layer2 "metal1") (purpose2 "drawing")
(encByLayer1 .4) (encByLayer2 .6))
(
  (w 1.8) (l .6)
  (row 1) (column 1)
  (xPitch 2.4)
  (yPitch 1.2)
  (xBias "center")
  (yBias "center")
)
)
```